

StarWind Virtual SAN: Configuration Guide for Red Hat oVirt [KVM], VSAN Deployed as a Controller Virtual Machine (CVM) using Web UI

2024

TECHNICAL PAPERS



Trademarks

“StarWind”, “StarWind Software” and the StarWind and the StarWind Software logos are registered trademarks of StarWind Software. “StarWind LSFS” is a trademark of StarWind Software which may be registered in some jurisdictions. All other trademarks are owned by their respective owners.

Changes

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to assure its accuracy, StarWind Software assumes no liability resulting from errors or omissions in this document, or from the use of the information contained herein. StarWind Software reserves the right to make changes in the product design without reservation and without notification to its users.

Technical Support and Services

If you have questions about installing or using this software, check this and other documents first - you will find answers to most of your questions on the [Technical Papers](#) webpage or in [StarWind Forum](#). If you need further assistance, please [contact us](#) .

About StarWind

StarWind is a pioneer in virtualization and a company that participated in the development of this technology from its earliest days. Now the company is among the leading vendors of software and hardware hyper-converged solutions. The company's core product is the years-proven StarWind Virtual SAN, which allows SMB and ROBO to benefit from cost-efficient hyperconverged IT infrastructure. Having earned a reputation of reliability, StarWind created a hardware product line and is actively tapping into hyperconverged and storage appliances market. In 2016, Gartner named StarWind “Cool Vendor for Compute Platforms” following the success and popularity of StarWind HyperConverged Appliance. StarWind partners with world-known companies: Microsoft, VMware, Veeam, Intel, Dell, Mellanox, Citrix, Western Digital, etc.

Copyright ©2009-2018 StarWind Software Inc.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of StarWind Software.

Annotation

Relevant Products

StarWind Virtual SAN (VSAN)

Purpose

This guide provides instructions for deploying and configuring StarWind Virtual SAN® Controller Virtual Machine (CVM) within the Red Hat oVirt [KVM] environment and creating StarWind devices using the Web UI. It encompasses essential aspects such as system requirements, RAID settings, best practices, and preliminary setup steps, ensuring a successful and efficient deployment.

Audience

Intended for IT specialists, system administrators, and professionals who are interested in deploying and configuring StarWind Virtual SAN CVM with Red Hat oVirt [KVM]

Expected Result

Upon completing this guide, users will possess a thorough understanding of the deployment and configuration process of StarWind Virtual SAN CVM within the Red Hat oVirt [KVM] environment.

Starwind Vsan System Requirements

Prior to installing StarWind Virtual SAN, please make sure that the system meets the requirements, which are available via the following link:

<https://www.starwindsoftware.com/system-requirements>

Recommended RAID settings for HDD and SSD disks:


<https://knowledgebase.starwindsoftware.com/guidance/recommended-raid-settings-for-hdd-and-ssd-disks/>

Please read StarWind Virtual SAN Best Practices document for additional information:

<https://www.starwindsoftware.com/resource-library/starwind-virtual-san-best-practices>

Pre-Configuring The Kvm Hosts

The diagram below illustrates the network and storage configuration of the solution:



1. Make sure that a oVirt engine is installed on a separate host.
2. Deploy oVirt on each server and add them to oVirt engine.
3. Define at least 2x network interfaces on each node that will be used for the Synchronization and iSCSI/StarWind heartbeat traffic. Do not use iSCSI/Heartbeat and Synchronization channels over the same physical link. Synchronization and iSCSI/Heartbeat links can be connected either via redundant switches or directly between the nodes (see diagram above).
4. Separate Logical Networks should be created for iSCSI and Synchronization traffic based on the selected before iSCSI and Synchronization interfaces. Using oVirt engine Networking page create two Logical Networks: one for the iSCSI/StarWind Heartbeat channel (iSCSI) and another one for the Synchronization channel (Sync).
5. Add physical NIC to Logical network on each host and configure static IP addresses. In this document, the 172.16.10.x subnet is used for iSCSI/StarWind heartbeat traffic, while 172.16.20.x subnet is used for the Synchronization traffic.

NOTE: In case NIC supports SR-IOV, enable it for the best performance. Contact support for additional details.

Enabling Multipath Support

8. Connect to server via ssh.

9. Create file /etc/multipath/conf.d/starwind.conf with the following content:

```
devices{
    device{
        vendor "STARWIND"
        product "STARWIND*"
        path_grouping_policy multibus
        path_checker "tur"
        failback immediate
        path_selector "round-robin 0"
        rr_min_io 3
        rr_weight uniform
        hardware_handler "1 alua"
    }
}
```

10. Restart multipathd service.

```
systemctl restart multipathd
```

11. Repeat the same procedure on the other server.

Creating NFS share

1. Make sure that each host has free storage to create NFS share.
2. Enable nfs server and rpcbind services.

```
systemctl enable --now nfs-server rpcbind
```

3. Create directory for NFS share.

```
mkdir -p /mnt/nfs
```

4. Change rights and owner of the share to KVM

```
chmod 0775 /mnt/nfs/
```

```
chown -R nobody:users /mnt/nfs/
```

5. Add NFS share to /etc/exports file.

```
vi /etc/exports  
/mnt/nfs/ *(rw,anonuid=36,anongid=36)
```

6. Restart NFS server service.

```
systemctl restart nfs-server
```

7. Check that share has been exported.

```
exportfs -rvv
```

8. Add firewall rules for NFS.


```
firewall-cmd --add-service={nfs,nfs3,rpc-bind} --permanent  
firewall-cmd --reload
```

Deploying Starwind Virtual San Cvm


1. Download StarWind VSAN CVM KVM: [VSAN by StarWind: Overview](#)
2. Extract the VM StarWindCVM.ova file from the downloaded archive.
3. Upload StarWindCVM.ova file to the oVirt Host via any SFTP client.
4. Change owner of the StarWindCVM.ova.

```
chown -R nobody:users /mnt/nfs/
```


5. Login to oVirt and open Compute -> Virtual Machines page. Choose Import.



6. Specify path to .ova file and choose VM to import. Click Next.



7. Verify VM settings and configure networks. Click OK.



8. Repeat all the steps from this section on other oVirt hosts.

Initial Configuration Wizard

1. Start StarWind Virtual SAN CVM.

2. Launch VM console to see the VM boot process and get the IPv4 address of the Management network interface.

NOTE: in case VM has no IPv4 address obtained from a DHCP server, use the Text-based User Interface (TUI) to set up a Management network.

3. Using the web browser, open a new tab and enter the VM IPv4 address to open StarWind VSAN Web Interface. Click "Advanced" and then "Continue to..."



Your connection is not private

Attackers might be trying to steal your information from **192.168.12.206** (for example, passwords, messages, or credit cards). [Learn more](#)

NET:ERR_CERT_AUTHORITY_INVALID


Hide advanced

Back to safety


This server could not prove that it is **192.168.12.206**; its security certificate is not trusted by your computer's operating system. This may be caused by a misconfiguration or an attacker intercepting your connection.

[Proceed to 192.168.12.206 \(unsafe\)](#)


4. StarWind VSAN web UI welcomes you, and the “Initial Configuration” wizard will guide you through the deployment process.



5. In the following step, upload the license file.




6. Read and accept the End User License Agreement to proceed.



7. Review or edit the Network settings and click Next.


NOTE: Static network settings are recommended for the configuration.



The screenshot shows the 'StarWind Appliance Initial configuration' window. On the left sidebar, the 'Management network' step is selected. The main area is titled 'Configure management network' and includes instructions to specify a unique IP address. A table lists network details for the 'ens160' interface. Below the table, there are optional fields for DNS servers and NTP settings. 'Back' and 'Next' buttons are at the bottom right.


NIC	Model	Bandwidth	MAC address	IP address	Netmask	Gateway
ens160	82574L Gigabit Ne...	1 Gbit	00:50:56:9C:E...	192.168.12.206	255.255.254.0	192.168.12.1

8. Specify the hostname for the virtual machine and click Next.




The screenshot shows the 'StarWind Appliance Initial configuration' window. On the left sidebar, the 'Static hostname' step is selected. The main area is titled 'Verify hostname' and includes instructions to check the current appliance hostname. A text field shows the hostname 'SW1'. 'Back' and 'Next' buttons are at the bottom right.

9. Create an administrator account. Click Next.




The screenshot shows the 'StarWind Appliance Initial configuration' window. On the left sidebar, the steps are: License (checked), EULA (checked), Management network (checked), Static hostname (checked), Administrator account (selected), Summary, and Configuration. The main area is titled 'Create administrator account' with the instruction 'Specify new credentials for the appliance administrator account'. It contains three input fields: 'Username' with the value 'admin', 'Password' (masked with dots), and 'Confirm password' (masked with dots). Below these are optional fields for 'Full name' and 'E-mail'. At the bottom right are 'Back' and 'Next' buttons.

10. Review your settings selection before setting up StarWind VSAN.




The screenshot shows the 'StarWind Appliance Initial configuration' window at the 'Review summary' step. The left sidebar now has 'Summary' selected. The main area is titled 'Review summary' and contains three sections: 'License type' showing 'License' and 'Paid 3 Nodes'; 'Network settings' showing 'Interface' as 'ens160 (82574L Gigabit Network Connection)', 'Bandwidth' as '1 Gbit', 'MTU' as '1500', 'IP address' as '192.168.12.206', and 'Appliance hostname' as 'SW1'; and 'Credentials' showing 'Administrator username' as 'admin'. At the bottom right are 'Back' and 'Configure' buttons.

11. Please standby until the Initial Configuration Wizard configures StarWind VSAN for you.



12. The appliance is set and ready. Click on the Done button to install the StarWind vCenter Plugin right now or uncheck the checkbox to skip this step and proceed to the [Login page](#).




13. Repeat the initial configuration on other StarWind CVMs that will be used to create 2-node or 3-node HA shared storage.

Add Appliance


To create 2-way or 3-way synchronously replicated highly available storage, add partner appliances that use the same license key.

1. Add StarWind appliance(s) in the web console, on the Appliances page.


NOTE: The newly added appliance will be linked to already connected partners.




2. Provide credentials of partner appliance.



3. Wait for connection and validation of settings.




4. Review the summary and click “Add appliance”.




Configure Ha Networking

1. Launch the “Configure HA Networking” wizard.



2. Select appliances for network configuration.


NOTE: the number of appliances to select is limited by your license, so can be either two or three appliances at a time.




3. Configure the “Data” network. Select interfaces to carry storage traffic, configure them with static IP addresses in unique networks, and specify subnet masks:

- assign and configure at least one interface on each node
- for redundant configuration, select two interfaces on each node
- ensure interfaces are connected to client hosts directly or through redundant switches

4. Assign MTU value to all selected network adapters, e.g. 1500 or 9000. Ensure the switches have the same MTU value set.



5. Click Next to validate Data network settings.




6. Configure the “Replication” network. Select interfaces to carry storage traffic, configure them with static IP addresses in unique networks, and specify subnet masks:


- assign and configure at least one interface on each node
- for redundant configuration, select two interfaces on each node


- ensure interfaces are connected to client hosts directly or through redundant switches

7. Assign MTU value to all selected network adapters, e.g. 1500 or 9000. Ensure the switches have the same MTU value set.




8. Click Next to validate the Replication network settings completion.





9. Review the summary and click Configure.



Add Physical Disks

Attach storage to StarWind Virtual SAN Controller VM:

- the physical hosts have all the drives connected through an HBA or RAID controller
- HBA or RAID controller will be added via a DirectPath I/O passthrough device to a StarWind CVM. Follow the instructions from the VMware on how to add a RAID controller as a PCI device to StarWind VM:
<https://docs.vmware.com/en/VMware-vSphere/8.0/vsphere-esxi-host-client/GUID-2B6D43A6-9598-47C4-A2E7-5924E3367BB6.html>
- StarWind CVM is installed on each server that is used to configure highly available storage.
- it is recommended to install StarWind CVM on a separate storage device available to the hypervisor host (e.g. SSD, HDD, etc.).
- for VMware vSphere environments, the disks can be added to StarWind VM as RDM. The link to VMware documentation is below:
https://docs.vmware.com/en/VMware-vSphere/7.0/com.vmware.vsphere.vm_admin.doc/GUID-4236E44E-E11F-4EDD-8CC0-12BA664BB811.html

NOTE: In order to make RDM and VMDK disks available for StarWind devices in StarWind CVM Version 20231016 (build 15260), please follow the steps below.

- stop service

```
sudo systemctl stop starwind-san-and-nas-console
```

- get VMDK/RDM/ device letter using lsblk command

```
lsblk |grep -v sda # sda - is excluded system drive.
```

- edit config file


```
sudo nano /opt/starwind/starwind-san-and-nas-console/appsettings.json
```

- add lines to the file, previously setting the disk letters to config (e.g. sdb, sdc)

```
"HardwareRaidImulation": {"PhysicalDisks": [ "sdb", "sdc" ]
},
```



- start service

```
sudo systemctl start starwind-san-and-nas-console
```




Create Storage Pool


1. Click the “Add” button to create a storage pool.
2. Select two storage nodes to create a storage pool on them simultaneously.



3. Select physical disks to include in the storage pool name and click the “Next” button.
NOTE: Select identical type and number of disks on each storage node to create identical storage pools.



4. Select one of the preconfigured storage profiles or create a redundancy layout for the new storage pool manually according to your redundancy, capacity, and performance requirements.




Hardware RAID, Linux Software RAID, and ZFS storage pools are supported and integrated into the StarWind CVM web interface. To make easier the storage pool configuration, the preconfigured storage profiles are provided to configure the

recommended pool type and layout according to the direct-attached storage:



- hardware RAID – configures Hardware RAID’s virtual disk as a storage pool. It is available only if a hardware RAID controller is passed through to the CVM
- high performance – creates Linux Software RAID-10 to maximize storage performance while maintaining redundancy
- high capacity – creates Linux Software RAID-5 to maximize storage capacity while maintaining redundancy
- better redundancy – creates ZFS Stripped RAID-Z2 (RAID 60)) to maximize redundancy while maintaining high storage capacity
- manual – allows users to configure any storage pool type and layout with attached storage

5. Review “Summary” and click the “Create” button to create the pools on storage servers simultaneously.




Create Volume


1. To create volumes, click the “Add” button.
2. Select two identical storage pools to create a volume simultaneously.




3. Specify volume name and capacity.



4. Select the Standard volume type.




5. Review “Summary” and click the “Create” button to create the pool.




Create Ha Lun

The LUN availability for StarWind LUN can be Standalone and High availability (2-way or 3-way replication) and is narrowed by your license.


1. To create a virtual disk, click the Add button.




2. Select the protocol.




3. Choose the “High availability” LUN availability type.



4. Select the appliances that will host the LUN. Partner appliances must have identical hardware configurations, including CPU, RAM, storage, and networking.




5. Select a volume to store the LUN data. Selected volumes must have identical storage configurations.




6. Select the “Heartbeat” failover strategy.


NOTE: To use the Node witness or the File share witness failover strategies, the appliances should have these features licensed.



7. Specify the HA LUN settings, e.g. name, size, and block size. Click Next.



8. Review “Summary” and click the “Create” button to create the LUN.



Creating Starwind Ha Luns Using Powershell

1. Open PowerShell ISE as Administrator.
2. Open StarWindX sample CreateHA_2.ps1 using PowerShell ISE. It can be found here:
 C:\Program Files\StarWind Software\StarWind\StarWindX\Samples\

```

1 param($addr="192.168.12.10", $port=3261, $user="root", $password="starwind",
2       $addr2="192.168.12.11", $port2=$port, $user2=$user, $password2=$password,
3
4       #common
5       $initMethod="Clear",
6       $size=2048,
7       $sectorSize=512,
8       $failover=0,
9       $bmpType=1,
10      $bmpStrategy=0,
11
12      #primary node
13      $ImagePath="VSA Storage\mnt\crypted1",
14      $imageName="testha02",
15      $createImage=$true,
16      $storageName="",
17      $targetAlias="target02",
18      $autoSynch=$true,
19      $poolName="pool1",
20      $syncSessionCount=1,
21      $saluaOptimized=$true,
22      $cacheMode="none",
23      $cacheSize=0,
24      $syncInterface="#p2={0}:3260" -f "172.16.10.20",
25      $hbInterface="#p2=172.16.20.20:3260",
26      $createTarget=$true,
27      $bmpFolderPath="",
28
29      #secondary node
30      $ImagePath2="VSA Storage\mnt\crypted1",
31      $imageName2="testha02",
32      $createImage2=$true,
33      $storageName2="",
34      $targetAlias2="target02",
35      $autoSynch2=$true,
36      $poolName2="pool1",
37      $syncSessionCount2=1,
38      $saluaOptimized2=$false,
39      $cacheMode2=$cacheMode,
40      $cacheSize2=$cacheSize,
41      $syncInterface2="#p1={0}:3260" -f "172.16.10.10",
42      $hbInterface2="#p1=172.16.10.10:3260",
43      $createTarget2=$true,
44      $bmpFolderPath2="",
45
46      )
47
48      Import-Module StarWindX
49
50      try
51      {
52          Enable-SWXLog -level SW_LOG_LEVEL_DEBUG
53
54          $server = New-SWServer -host $addr -port $port -user $user -password $password
55
56          $server.Connect()
57
58          #-----
59
60      }
61      catch
62      {
63      }
64
65      #-----
66
67      #-----
68
69      #-----
70
71      #-----
72
73      #-----
74
75      #-----
76
77      #-----
78
79      #-----
80
81      #-----
82
83      #-----
84
85      #-----
86
87      #-----
88
89      #-----
90
91      #-----
92
93      #-----
94
95      #-----
96
97      #-----
98
99      #-----
100
101      #-----
102
103      #-----
104
105      #-----
106
107      #-----
108
109      #-----
110
111      #-----
112
113      #-----
114
115      #-----
116
117      #-----
118
119      #-----
120
121      #-----
122
123      #-----
124
125      #-----
126
127      #-----
128
129      #-----
130
131      #-----
132
133      #-----
134
135      #-----
136
137      #-----
138
139      #-----
140
141      #-----
142
143      #-----
144
145      #-----
146
147      #-----
148
149      #-----
150
151      #-----
152
153      #-----
154
155      #-----
156
157      #-----
158
159      #-----
160
161      #-----
162
163      #-----
164
165      #-----
166
167      #-----
168
169      #-----
170
171      #-----
172
173      #-----
174
175      #-----
176
177      #-----
178
179      #-----
180
181      #-----
182
183      #-----
184
185      #-----
186
187      #-----
188
189      #-----
190
191      #-----
192
193      #-----
194
195      #-----
196
197      #-----
198
199      #-----
200
201      #-----
202
203      #-----
204
205      #-----
206
207      #-----
208
209      #-----
210
211      #-----
212
213      #-----
214
215      #-----
216
217      #-----
218
219      #-----
220
221      #-----
222
223      #-----
224
225      #-----
226
227      #-----
228
229      #-----
230
231      #-----
232
233      #-----
234
235      #-----
236
237      #-----
238
239      #-----
240
241      #-----
242
243      #-----
244
245      #-----
246
247      #-----
248
249      #-----
250
251      #-----
252
253      #-----
254
255      #-----
256
257      #-----
258
259      #-----
260
261      #-----
262
263      #-----
264
265      #-----
266
267      #-----
268
269      #-----
270
271      #-----
272
273      #-----
274
275      #-----
276
277      #-----
278
279      #-----
280
281      #-----
282
283      #-----
284
285      #-----
286
287      #-----
288
289      #-----
290
291      #-----
292
293      #-----
294
295      #-----
296
297      #-----
298
299      #-----
300
301      #-----
302
303      #-----
304
305      #-----
306
307      #-----
308
309      #-----
310
311      #-----
312
313      #-----
314
315      #-----
316
317      #-----
318
319      #-----
320
321      #-----
322
323      #-----
324
325      #-----
326
327      #-----
328
329      #-----
330
331      #-----
332
333      #-----
334
335      #-----
336
337      #-----
338
339      #-----
340
341      #-----
342
343      #-----
344
345      #-----
346
347      #-----
348
349      #-----
350
351      #-----
352
353      #-----
354
355      #-----
356
357      #-----
358
359      #-----
360
361      #-----
362
363      #-----
364
365      #-----
366
367      #-----
368
369      #-----
370
371      #-----
372
373      #-----
374
375      #-----
376
377      #-----
378
379      #-----
380
381      #-----
382
383      #-----
384
385      #-----
386
387      #-----
388
389      #-----
390
391      #-----
392
393      #-----
394
395      #-----
396
397      #-----
398
399      #-----
400
401      #-----
402
403      #-----
404
405      #-----
406
407      #-----
408
409      #-----
410
411      #-----
412
413      #-----
414
415      #-----
416
417      #-----
418
419      #-----
420
421      #-----
422
423      #-----
424
425      #-----
426
427      #-----
428
429      #-----
430
431      #-----
432
433      #-----
434
435      #-----
436
437      #-----
438
439      #-----
440
441      #-----
442
443      #-----
444
445      #-----
446
447      #-----
448
449      #-----
450
451      #-----
452
453      #-----
454
455      #-----
456
457      #-----
458
459      #-----
460
461      #-----
462
463      #-----
464
465      #-----
466
467      #-----
468
469      #-----
470
471      #-----
472
473      #-----
474
475      #-----
476
477      #-----
478
479      #-----
480
481      #-----
482
483      #-----
484
485      #-----
486
487      #-----
488
489      #-----
490
491      #-----
492
493      #-----
494
495      #-----
496
497      #-----
498
499      #-----
500
501      #-----
502
503      #-----
504
505      #-----
506
507      #-----
508
509      #-----
510
511      #-----
512
513      #-----
514
515      #-----
516
517      #-----
518
519      #-----
520
521      #-----
522
523      #-----
524
525      #-----
526
527      #-----
528
529      #-----
530
531      #-----
532
533      #-----
534
535      #-----
536
537      #-----
538
539      #-----
540
541      #-----
542
543      #-----
544
545      #-----
546
547      #-----
548
549      #-----
550
551      #-----
552
553      #-----
554
555      #-----
556
557      #-----
558
559      #-----
560
561      #-----
562
563      #-----
564
565      #-----
566
567      #-----
568
569      #-----
570
571      #-----
572
573      #-----
574
575      #-----
576
577      #-----
578
579      #-----
580
581      #-----
582
583      #-----
584
585      #-----
586
587      #-----
588
589      #-----
590
591      #-----
592
593      #-----
594
595      #-----
596
597      #-----
598
599      #-----
600
601      #-----
602
603      #-----
604
605      #-----
606
607      #-----
608
609      #-----
610
611      #-----
612
613      #-----
614
615      #-----
616
617      #-----
618
619      #-----
620
621      #-----
622
623      #-----
624
625      #-----
626
627      #-----
628
629      #-----
630
631      #-----
632
633      #-----
634
635      #-----
636
637      #-----
638
639      #-----
640
641      #-----
642
643      #-----
644
645      #-----
646
647      #-----
648
649      #-----
650
651      #-----
652
653      #-----
654
655      #-----
656
657      #-----
658
659      #-----
660
661      #-----
662
663      #-----
664
665      #-----
666
667      #-----
668
669      #-----
670
671      #-----
672
673      #-----
674
675      #-----
676
677      #-----
678
679      #-----
680
681      #-----
682
683      #-----
684
685      #-----
686
687      #-----
688
689      #-----
690
691      #-----
692
693      #-----
694
695      #-----
696
697      #-----
698
699      #-----
700
701      #-----
702
703      #-----
704
705      #-----
706
707      #-----
708
709      #-----
710
711      #-----
712
713      #-----
714
715      #-----
716
717      #-----
718
719      #-----
720
721      #-----
722
723      #-----
724
725      #-----
726
727      #-----
728
729      #-----
730
731      #-----
732
733      #-----
734
735      #-----
736
737      #-----
738
739      #-----
740
741      #-----
742
743      #-----
744
745      #-----
746
747      #-----
748
749      #-----
750
751      #-----
752
753      #-----
754
755      #-----
756
757      #-----
758
759      #-----
760
761      #-----
762
763      #-----
764
765      #-----
766
767      #-----
768
769      #-----
770
771      #-----
772
773      #-----
774
775      #-----
776
777      #-----
778
779      #-----
780
781      #-----
782
783      #-----
784
785      #-----
786
787      #-----
788
789      #-----
790
791      #-----
792
793      #-----
794
795      #-----
796
797      #-----
798
799      #-----
800
801      #-----
802
803      #-----
804
805      #-----
806
807      #-----
808
809      #-----
810
811      #-----
812
813      #-----
814
815      #-----
816
817      #-----
818
819      #-----
820
821      #-----
822
823      #-----
824
825      #-----
826
827      #-----
828
829      #-----
830
831      #-----
832
833      #-----
834
835      #-----
836
837      #-----
838
839      #-----
840
841      #-----
842
843      #-----
844
845      #-----
846
847      #-----
848
849      #-----
850
851      #-----
852
853      #-----
854
855      #-----
856
857      #-----
858
859      #-----
860
861      #-----
862
863      #-----
864
865      #-----
866
867      #-----
868
869      #-----
870
871      #-----
872
873      #-----
874
875      #-----
876
877      #-----
878
879      #-----
880
881      #-----
882
883      #-----
884
885      #-----
886
887      #-----
888
889      #-----
890
891      #-----
892
893      #-----
894
895      #-----
896
897      #-----
898
899      #-----
900
901      #-----
902
903      #-----
904
905      #-----
906
907      #-----
908
909      #-----
910
911      #-----
912
913      #-----
914
915      #-----
916
917      #-----
918
919      #-----
920
921      #-----
922
923      #-----
924
925      #-----
926
927      #-----
928
929      #-----
930
931      #-----
932
933      #-----
934
935      #-----
936
937      #-----
938
939      #-----
940
941      #-----
942
943      #-----
944
945      #-----
946
947      #-----
948
949      #-----
950
951      #-----
952
953      #-----
954
955      #-----
956
957      #-----
958
959      #-----
960
961      #-----
962
963      #-----
964
965      #-----
966
967      #-----
968
969      #-----
970
971      #-----
972
973      #-----
974
975      #-----
976
977      #-----
978
979      #-----
980
981      #-----
982
983      #-----
984
985      #-----
986
987      #-----
988
989      #-----
990
991      #-----
992
993      #-----
994
995      #-----
996
997      #-----
998
999      #-----
1000
1001      #-----
1002
1003      #-----
1004
1005      #-----
1006
1007      #-----
1008
1009      #-----
1010
1011      #-----
1012
1013      #-----
1014
1015      #-----
1016
1017      #-----
1018
1019      #-----
1020
1021      #-----
1022
1023      #-----
1024
1025      #-----
1026
1027      #-----
1028
1029      #-----
1030
1031      #-----
1032
1033      #-----
1034
1035      #-----
1036
1037      #-----
1038
1039      #-----
1040
1041      #-----
1042
1043      #-----
1044
1045      #-----
1046
1047      #-----
1048
1049      #-----
1050
1051      #-----
1052
1053      #-----
1054
1055      #-----
1056
1057      #-----
1058
1059      #-----
1060
1061      #-----
1062
1063      #-----
1064
1065      #-----
1066
1067      #-----
1068
1069      #-----
1070
1071      #-----
1072
1073      #-----
1074
1075      #-----
1076
1077      #-----
1078
1079      #-----
1080
1081      #-----
1082
1083      #-----
1084
1085      #-----
1086
1087      #-----
1088
1089      #-----
1090
1091      #-----
1092
1093      #-----
1094
1095      #-----
1096
1097      #-----
1098
1099      #-----
1100
1101      #-----
1102
1103      #-----
1104
1105      #-----
1106
1107      #-----
1108
1109      #-----
1110
1111      #-----
1112
1113      #-----
1114
1115      #-----
1116
1117      #-----
1118
1119      #-----
1120
1121      #-----
1122
1123      #-----
1124
1125      #-----
1126
1127      #-----
1128
1129      #-----
1130
1131      #-----
1132
1133      #-----
1134
1135      #-----
1136
1137      #-----
1138
1139      #-----
1140
1141      #-----
1142
1143      #-----
1144
1145      #-----
1146
1147      #-----
1148
1149      #-----
1150
1151      #-----
1152
1153      #-----
1154
1155      #-----
1156
1157      #-----
1158
1159      #-----
1160
1161      #-----
1162
1163      #-----
1164
1165      #-----
1166
1167      #-----
1168
1169      #-----
1170
1171      #-----
1172
1173      #-----
1174
1175      #-----
1176
1177      #-----
1178
1179      #-----
1180
1181      #-----
1182
1183      #-----
1184
1185      #-----
1186
1187      #-----
1188
1189      #-----
1190
1191      #-----
1192
1193      #-----
1194
1195      #-----
1196
1197      #-----
1198
1199      #-----
1200
1201      #-----
1202
1203      #-----
1204
1205      #-----
1206
1207      #-----
1208
1209      #-----
1210
1211      #-----
1212
1213      #-----
1214
1215      #-----
1216
1217      #-----
1218
1219      #-----
1220
1221      #-----
1222
1223      #-----
1224
1225      #-----
1226
1227      #-----
1228
1229      #-----
1230
1231      #-----
1232
1233      #-----
1234
1235      #-----
1236
1237      #-----
1238
1239      #-----
1240
1241      #-----
1242
1243      #-----
1244
1245      #-----
1246
1247      #-----
1248
1249      #-----
1250
1251      #-----
1252
1253      #-----
1254
1255      #-----
1256
1257      #-----
1258
1259      #-----
1260
1261      #-----
1262
1263      #-----
1264
1265      #-----
1266
1267      #-----
1268
1269      #-----
1270
1271      #-----
1272
1273      #-----
1274
1275      #-----
1276
1277      #-----
1278
1279      #-----
1280
1281      #-----
1282
1283      #-----
1284
1285      #-----
1286
1287      #-----
1288
1289      #-----
1290
1291      #-----
1292
1293      #-----
1294
1295      #-----
1296
1297      #-----
1298
1299      #-----
1300
1301      #-----
1302
1303      #-----
1304
1305      #-----
1306
1307      #-----
1308
1309      #-----
1310
1311      #-----
1312
1313      #-----
1314
1315      #-----
1316
1317      #-----
1318
1319      #-----
1320
1321      #-----
1322
1323      #-----
1324
1325      #-----
1326
1327      #-----
1328
1329      #-----
1330
1331      #-----
1332
1333      #-----
1334
1335      #-----
1336
1337      #-----
1338
1339      #-----
1340
1341      #-----
1342
1343      #-----
1344
1345      #-----
1346
1347      #-----
1348
1349      #-----
1350
1351      #-----
1352
1353      #-----
1354
1355      #-----
1356
1357      #-----
1358
1359      #-----
1360
1361      #-----
1362
1363      #-----
1364
1365      #-----
1366
1367      #-----
1368
1369      #-----
1370
1371      #-----
1372
1373      #-----
1374
1375      #-----
1376
1377      #-----
1378
1379      #-----
1380
1381      #-----
1382
1383      #-----
1384
1385      #-----
1386
1387      #-----
1388
1389      #-----
1390
1391      #-----
1392
1393      #-----
1394
1395      #-----
1396
1397      #-----
1398
1399      #-----
1400
1401      #-----
1402
1403      #-----
1404
1405      #-----
1406
1407      #-----
1408
1409      #-----
1410
1411      #-----
1412
1413      #-----
1414
1415      #-----
1416
1417      #-----
1418
1419      #-----
1420
1421      #-----
1422
1423      #-----
1424
1425      #-----
1426
1427      #-----
1428
1429      #-----
1430
1431      #-----
1432
1433      #-----
1434
1435      #-----
1436
1437      #-----
1438
1439      #-----
1440
1441      #-----
1442
1443      #-----
1444
1445      #-----
1446
1447      #-----
1448
1449      #-----
1450
1451      #-----
1452
1453      #-----
1454
1455      #-----
1456
1457      #-----
1458
1459      #-----
1460
1461      #-----
1462
1463      #-----
1464
1465      #-----
1466
1467      #-----
1468
1469      #-----
1470
1471      #-----
1472
1473      #-----
1474
1475      #-----
1476
1477      #-----
1478
1479      #-----
1480
1481      #-----
1482
1483      #-----
1484
1485      #-----
1486
1487      #-----
1488
1489      #-----
1490
1491      #-----
1492
1493      #-----
1494
1495      #-----
1496
1497      #-----
1498
1499      #-----
1500
1501      #-----
1502
1503      #-----
1504
1505      #-----
1506
1507      #-----
1508
1509      #-----
1510
1511      #-----
1512
1513      #-----
1514
1515      #-----
1516
1517      #-----
1518
1519      #-----
1520
1521      #-----
1522
1523      #-----
1524
1525      #-----
1526
1527      #-----
1528
1529      #-----
1530
1531      #-----
1532
1533      #-----
1534
1535      #-----
1536
1537      #-----
1538
1539      #-----
1540
1541      #-----
1542
1543      #-----
1544
1545      #-----
1546
1547      #-----
1548
1549      #-----
1550
1551      #-----
1552
1553      #-----
1554
1555      #-----
1556
1557      #-----
1558
1559      #-----
1560
1561      #-----
1562
1563      #-----
1564
1565      #-----
1566
1567      #-----
1568
1569      #-----
1570
1571      #-----
1572
1573      #-----
1574
1575      #-----
1576
1577      #-----
1578
1579      #-----
1580
1581      #-----
1582
1583      #-----
1584
1585      #-----
1586
1587      #-----
1588
1589      #-----
1590
1591      #-----
1592
1593      #-----
1594
1595      #-----
1596
1597      #-----
1598
1599      #-----
1600
1601      #-----
1602
1603      #-----
1604
1605      #-----
1606
1607      #-----
1608
1609      #-----
1610
1611      #-----
1612
1613      #-----
1614
1615      #-----
1616
1617      #-----
1618
1619      #-----
1620
1621      #-----
1622
1623      #-----
1624
1625      #-----
1626
1627      #-----
1628
1629      #-----
1630
1631      #-----
1632
1633      #-----
1634
1635      #-----
1636
1637      #-----
1638
1639      #-----
1640
1641      #-----
1642
1643      #-----
1644
1645      #-----
1646
1647      #-----
1648
1649      #-----
1650
1651      #-----
1652
1653      #-----
1654
1655      #-----
1656
1657      #-----
1658
1659      #-----
1660
1661      #-----
1662
1663      #-----
1664
1665      #-----
1666
1667      #-----
1668
1669      #-----
1670
1671      #-----
1672
1673      #-----
1674
1675      #-----
1676
1677      #-----
1678
1679      #-----
1680
1681      #-----
1682
1683      #-----
1684
1685      #-----
1686
1687      #-----
1688
1689      #-----
1690
1691      #-----
1692
1693      #-----
1694
1695      #-----
1696
1697      #-----
1698
1699      #-----
1700
1701      #-----
1702
1703      #-----
1704
1705      #-----
1706
1707      #-----
1708
1709      #-----
1710
1711      #-----
1712
1713      #-----
1714
1715      #-----
1716
1717      #-----
1718
1719      #-----
1720
1721      #-----
1722
1723      #-----
1724
1725      #-----
1726
1727      #-----
1728
1729      #-----
1730
1731      #-----
1732
1733      #-----
1734
1735      #-----
1736
1737      #-----
1738
1739      #-----
1740
1741      #-----
1742
1743      #-----
1744
1745      #-----
1746
1747      #-----
1748
1749      #-----
1750
1751      #-----
1752
1753      #-----
1754
1755      #-----
1756
1757      #-----
1758
1759      #-----
1760
1761      #-----
1762
1763      #-----
1764
1765      #-----
1766
1767      #-----
1768
1769      #-----
1770
1771      #-----
1772
1773      #-----
1774
1775      #-----
1776
1777      #-----
1778
1779      #-----
1780
1781      #-----
1782
1783      #-----
1784
1785      #-----
1786
1787      #-----
1788
1789      #-----
1790
1791      #-----
1792
1793      #-----
1794
1795      #-----
1796
1797      #-----
1798
1799      #-----
1800
1801      #-----
1802
1803      #-----
1804
1805      #-----
1806
1807      #-----
1808
1809      #-----
1810
1811      #-----
1812
1813      #-----
1814
1815      #-----
1816
1817      #-----
1818
1819      #-----
1820
1821      #-----
1822
1823      #-----
1824
1825      #-----
1826
1827      #-----
1828
1829      #-----
1830
1831      #-----
1832
1833      #-----
1834
1835      #-----
1836
1837      #-----
1838
1839      #-----
1840
1841      #-----
1842
1843      #-----
1844
1845      #-----
1846
1847      #-----
1848
1849      #-----
1850
1851      #-----
1852
1853      #-----
1854
1855      #-----
1856
1857      #-----
1858
1859      #-----
1860
1861      #-----
1862
1863      #-----
1864
1865      #-----
1866
1867      #-----
1868
1869      #-----
1870
1871      #-----
1872
1873      #-----
1874
1875      #-----
1876
1877      #-----
1878
1879      #-----
1880
1881      #-----
1882
1883      #-----
1884
1885      #-----
1886
1887      #-----
1888
1889      #-----
1890
1891      #-----
1892
1893      #-----
1894
1895      #-----
1896
1897      #-----
1898
1899      #-----
1900
1901      #-----
1902
1903      #-----
1904
1905      #-----
1906
1907      #-----
1908
1909      #-----
1910
1911      #-----
1912
1913      #-----
1914
1915      #-----
1916
1917      #-----
1918
1919      #-----
1920
1921      #-----
1922
1923      #-----
1924
1925      #-----
1926
1927      #-----
1928
1929      #-----
1930
1931      #-----
1932
1933      #-----
1934
1935      #-----
1936
1937      #-----
1938
1939      #-----
1940
1941      #-----
1942
1943      #-----
1944
1945      #-----
1946
1947      #-----
1948
1949      #-----
1950
1951      #-----
1952
1953      #-----
1954
1955      #-----
1956
```

```

        $bmpStrategy=0,
#primary node
    $imagePath="VSA Storage\mnt\crypted1",
    $imageName="testha02",
    $createImage=$true,
    $storageName="",
    $targetAlias="target02",
    $autoSynch=$true,
    $poolName="pool1",
    $syncSessionCount=1,
    $aluaOptimized=$true,
    $cacheMode="none",
    $cacheSize=0,
    $syncInterface="#p2={0}:3260" -f "172.16.20.20",
    $hbInterface="#p2={0}:3260" -f "172.16.10.20",
    $createTarget=$true,
    $bmpFolderPath="",
#secondary node
    $imagePath2="VSA Storage\mnt\crypted1",
    $imageName2="testha02",
    $createImage2=$true,
    $storageName2="",
    $targetAlias2="target02",
    $autoSynch2=$true,
    $poolName2="pool1",
    $syncSessionCount2=1,
    $aluaOptimized2=$false,
    $cacheMode2=$cacheMode,
    $cacheSize2=$cacheSize,
    $syncInterface2="#p1={0}:3260" -f "172.16.20.10",
    $hbInterface2="#p1={0}:3260" -f "172.16.10.10",
    $createTarget2=$true,
    $bmpFolderPath2=""
)
Import-Module StarWindX

try
{
    Enable-SWXLog -level SW_LOG_LEVEL_DEBUG

    $server = New-SWServer -host $addr -port $port -user
$user -password $password

    $server.Connect()

```

```

$firstNode = new-Object Node

$firstNode.HostName = $addr
$firstNode.HostPort = $port
$firstNode.Login = $user
$firstNode.Password = $password
$firstNode.ImagePath = $imagePath
$firstNode.ImageName = $imageName
$firstNode.Size = $size
$firstNode.CreateImage = $createImage
$firstNode.StorageName = $storageName
$firstNode.TargetAlias = $targetAlias
$firstNode.AutoSynch = $autoSynch
$firstNode.SyncInterface = $syncInterface
$firstNode.HBInterface = $hbInterface
$firstNode.PoolName = $poolName
$firstNode.SyncSessionCount = $syncSessionCount
$firstNode.ALUAOptimized = $aluaOptimized
$firstNode.CacheMode = $cacheMode
$firstNode.CacheSize = $cacheSize
$firstNode.FailoverStrategy = $failover
$firstNode.CreateTarget = $createTarget
$firstNode.BitmapStoreType = $bmpType
$firstNode.BitmapStrategy = $bmpStrategy
$firstNode.BitmapFolderPath = $bmpFolderPath
#
# device sector size. Possible values: 512 or 4096(May
be incompatible with some clients!) bytes.
#
$firstNode.SectorSize = $sectorSize
$secondNode = new-Object Node

$secondNode.HostName = $addr2
$secondNode.HostPort = $port2
$secondNode.Login = $user2
$secondNode.Password = $password2
$secondNode.ImagePath = $imagePath2
$secondNode.ImageName = $imageName2
$secondNode.CreateImage = $createImage2
$secondNode.StorageName = $storageName2
$secondNode.TargetAlias = $targetAlias2
$secondNode.AutoSynch = $autoSynch2
$secondNode.SyncInterface = $syncInterface2
$secondNode.HBInterface = $hbInterface2
  
```

```

    $secondNode.SyncSessionCount = $syncSessionCount2
    $secondNode.ALUAOptimized = $aluaOptimized2
    $secondNode.CacheMode = $cacheMode2
    $secondNode.CacheSize = $cacheSize2
    $secondNode.FailoverStrategy = $failover
    $secondNode.CreateTarget = $createTarget2
    $secondNode.BitmapFolderPath = $bmpFolderPath2
    $device = Add-HADevice -server $server -firstNode
    $firstNode -secondNode $secondNode -initMethod $initMethod
    while ($device.SyncStatus -ne
    [SwHaSyncStatus]::SW_HA_SYNC_STATUS_SYNC)
    {
        $syncPercent =
    $device.GetPropertyValue("ha_synch_percent")
        Write-Host "Synchronizing: $($syncPercent)%" -
    foreground yellow

        Start-Sleep -m 2000

        $device.Refresh()
    }
  }
  catch
  {
      Write-Host $_ -foreground red
  }
  finally
  {
      $server.Disconnect()
  }
}

```

Detailed explanation of script parameters:

-addr, -addr2 — partner nodes IP address.

Format: string. Default value: 192.168.0.1, 192.168.0.1

allowed values: localhost, IP-address

-port, -port2 — local and partner node port.

Format: string. Default value: 3261

-user, -user2 — local and partner node user name.

Format: string. Default value: root

-password, -password2 — local and partner node user password.

Format: string. Default value: starwind

#common

-initMethod –

Format: string. Default value: Clear

-size – set size for HA-devcie (MB)

Format: integer. Default value: 12

-sectorSize – set sector size for HA-device

Format: integer. Default value: 512

allowed values: 512, 4096

-failover – set type failover strategy

Format: integer. Default value: 0 (Heartbeat)

allowed values: 0, 1 (Node Majority)

-bmpType – set bitmap type, is set for both partners at once

Format: integer. Default value: 1 (RAM)

allowed values: 1, 2 (DISK)

-bmpStrategy – set journal strategy, is set for both partners at once

Format: integer. Default value: 0

allowed values: 0, 1 – Best Performance (Failure), 2 – Fast Recovery (Continuous)

#primary node

-imagePath – set path to store the device file

Format: string. Default value: My computer\C\starwind". For Linux the following format should be used: "VSA Storage\mnt\mount_point"

-imageName – set name device

Format: string. Default value: masterImg21

-createImage – set create image file

Format: boolean. Default value: true

-targetAlias – set alias for target

Format: string. Default value: targetha21

-poolName – set storage pool

Format: string. Default value: pool1

-aluaOptimized – set Alua Optimized

Format: boolean. Default value: true

-cacheMode – set type L1 cache (optional parameter)

Format: string. Default value: wb

allowed values: none, wb, wt

-cacheSize – set size for L1 cache in MB (optional parameter)

Format: integer. Default value: 128

allowed values: 1 and more

-syncInterface – set sync channel IP-address from partner node

Format: string. Default value: "#p2={0}:3260"

-hbInterface – set heartbeat channel IP-address from partner node

Format: string. Default value: ""

-createTarget – set creating target

Format: string. Default value: true

Even if you do not specify the parameter -createTarget, the target will be created

automatically.

If the parameter is set as `-createTarget $false`, then an attempt will be made to create the device with existing targets, the names of which are specified in the `-targetAlias` (targets must already be created)

`-bmpFolderPath` – set path to save bitmap file

Format: string.

#secondary node

`-imagePath2` – set path to store the device file

Format: string. Default value: "My computer\C\starwind". For Linux the following format should be used: "VSA Storage\mnt\mount_point"

`-imageName2` – set name device

Format: string. Default value: masterImg21

`-createImage2` – set create image file

Format: boolean. Default value: true

`-targetAlias2` – set alias for targetFormat: string.

Default value: targetha22

`-poolName2` – set storage pool

Format: string. Default value: pool1

`-aluaOptimized2` – set Alua Optimized

Format: boolean. Default value: true

`-cacheMode2` – set type L1 cache (optional parameter)

Format: string. Default value: wb

allowed values: wb, wt

`-cacheSize2` – set size for L1 cache in MB (optional parameter)

Format: integer. Default value: 128

allowed values: 1 and more

`-syncInterface2` – set sync channel IP-address from partner node

Format: string. Default value: "#p1={0}:3260"

`-hbInterface2` – set heartbeat channel IP-address from partner node

Format: string. Default value: ""

`-createTarget2` – set creating target

Format: string. Default value: true

Even if you do not specify the parameter `-createTarget`, the target will be created automatically.If the parameter is set as `-createTarget $false`, then an attempt will be made to create the device with existing targets, the names of which are specified in the `-targetAlias` (targets must already be created)

`-bmpFolderPath2` – set path to save bitmap file

Format: string.

Selecting The Failover Strategy

StarWind provides 2 options for configuring a failover strategy:

Heartbeat

The Heartbeat failover strategy allows avoiding the “split-brain” scenario when the HA cluster nodes are unable to synchronize but continue to accept write commands from the initiators independently. It can occur when all synchronization and heartbeat channels disconnect simultaneously, and the partner nodes do not respond to the node’s requests. As a result, StarWind service assumes the partner nodes to be offline and continues operations on a single-node mode using data written to it.

If at least one heartbeat link is online, StarWind services can communicate with each other via this link. The device with the lowest priority will be marked as not synchronized and get subsequently blocked for the further read and write operations until the synchronization channel resumption. At the same time, the partner device on the synchronized node flushes data from the cache to the disk to preserve data integrity in case the node goes down unexpectedly. It is recommended to assign more independent heartbeat channels during the replica creation to improve system stability and avoid the “split-brain” issue.

With the heartbeat failover strategy, the storage cluster will continue working with only one StarWind node available.

Node Majority

The Node Majority failover strategy ensures the synchronization connection without any additional heartbeat links. The failure-handling process occurs when the node has detected the absence of the connection with the partner.

The main requirement for keeping the node operational is an active connection with more than half of the HA device’s nodes. Calculation of the available partners is based on their “votes”.


In case of a two-node HA storage, all nodes will be disconnected if there is a problem on the node itself, or in communication between them. Therefore, the Node Majority failover strategy requires the addition of the third Witness node or file share (SMB) which participates in the nodes count for the majority, but neither contains data on it nor is involved in processing clients’ requests. In case an HA device is replicated between 3 nodes, no Witness node is required.

With Node Majority failover strategy, failure of only one node can be tolerated. If two nodes fail, the third node will also become unavailable to clients’ requests.


Please select the required option:

Provisioning Starwind Ha Storage To Ovirt Hosts


1. Login to oVirt engine and open Storage -> Domain. Click New Domain.




2. Choose Storage Type - iSCSI, Host and Name of Storage Domain. Discover targets via iSCSI links, which were previously configured. Click Login All.



3. Add LUN from each iSCSI target. Click OK.



4. Storage Domain will be added to the list of Domain and can be used as a storage for VMs.



5. Login to each host and verify that multipathing policy has been applied using the following command.








```
multipath -ll
```

```
[root@sw-demo-node-01 ~]# multipath -ll
22ebelf66db375fb0 dm-13 STARWIND,STARWIND
size=500G features='1 queue_if_no_path' hwhandler='1 alua' wp=rw
`-+- policy='round-robin 0' prio=50 status=active
   |- 16:0:0:0 sdb      8:16 active ready running
   `-- 17:0:0:0 sdc     8:32 active ready running
```

Conclusion

Setting up StarWind Virtual SAN CVM within the Red Hat oVirt [KVM] environment is significant for organizations looking for a robust, VM-centric and highly-available storage solution. This guide ensures that IT professionals are armed with the essential knowledge and resources for a seamless deployment and configuration.

Contacts

US Headquarters	EMEA and APAC
 +1 617 829 44 95	 +44 2037 691 857 (United Kingdom)
 +1 617 507 58 45	 +49 800 100 68 26 (Germany)
 +1 866 790 26 46	 +34 629 03 07 17 (Spain and Portugal)
	 +33 788 60 30 06 (France)

Customer Support Portal: <https://www.starwind.com/support>

Support Forum: <https://www.starwind.com/forums>

Sales: sales@starwind.com

General Information: info@starwind.com



StarWind Software, Inc. 100 Cummings Center Suite 224-C Beverly MA 01915, USA
www.starwind.com ©2024, StarWind Software Inc. All rights reserved.