StarWind Virtual Tape Library: Configuration Guide for IBM i, VTL Deployed as a Windows Application using GUI

2026

TECHNICAL PAPERS

Trademarks

“StarWind”, “StarWind Software” and the StarWind and the StarWind Software logos are registered trademarks of StarWind Software. “StarWind LSFS” is a trademark of StarWind Software which may be registered in some jurisdictions. All other trademarks are owned by their respective owners.

Changes

The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made in the preparation of this document to assure its accuracy, StarWind Software assumes no liability resulting from errors or omissions in this document, or from the use of the information contained herein. StarWind Software reserves the right to make changes in the product design without reservation and without notification to its users.

Technical Support and Services

If you have questions about installing or using this software, check this and other documents first - you will find answers to most of your questions on the Technical Papers webpage or in StarWind Forum. If you need further assistance, please contact us .

About StarWind

StarWind is a pioneer in virtualization and a company that participated in the development of this technology from its earliest days. Now the company is among the leading vendors of software and hardware hyper-converged solutions. The company’s core product is the years-proven StarWind Virtual SAN, which allows SMB and ROBO to benefit from cost-efficient hyperconverged IT infrastructure. Having earned a reputation of reliability, StarWind created a hardware product line and is actively tapping into hyperconverged and storage appliances market. In 2016, Gartner named StarWind “Cool Vendor for Compute Platforms” following the success and popularity of StarWind HyperConverged Appliance. StarWind partners with world-known companies: Microsoft, VMware, Veeam, Intel, Dell, Mellanox, Citrix, Western Digital, etc.

Copyright ©2009-2018 StarWind Software Inc.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of StarWind Software.

Annotation

Relevant products

This guide is applicable for StarWind VTL (build version 15313).

Purpose

StarWind Virtual Tape Library (VTL) is a software solution that allows you to emulate physical Tape Libraries while storing data on hard disk drives. The solution targets companies that want to completely quit using the physical Tape Library, as well as simplify and accelerate the process of data backup and recovery. If required, the virtual tapes also can be replicated to the cloud (Amazon S3, Backblaze, Microsoft Azure, Wasabi, etc.) using StarWind Cloud Replicator.

This document outlines how to configure a StarWind VTL for IBM i and includes steps on how to connect it to IBM i using IBM Navigator or SQL service commands on a choice.

Audience

This technical guide is intended for storage and virtualization architects, system administrators, and partners designing virtualized environments using StarWind Virtual Tape Library (VTL).

Expected result

The end result of following this guide will be a fully configured StarWind VTL which is connected to IBM i and ready-to-use.

Prerequisites

This document assumes that StarWind VTL will be deployed on a host running Windows Server 2022 (or Windows Server 2019). The Windows-based host and IBM i host got directly connected links, with a dedicated network configured and used to connect iSCSI target, provided by StarWind.

StarWind VTL system requirements


Prior to installing StarWind Virtual SAN, please make sure that the system meets the requirements, which are available via the following link:
https://www.starwindsoftware.com/system-requirements#virtual-tape-library

Recommended RAID settings for HDD and SSD disks:
https://knowledgebase.starwindsoftware.com/guidance/recommended-raid-settings-for-hdd-and-ssd-disks/


IMPORTANT NOTE: In order to fit the ransomware resiliency, the VTL should be located on the dedicated storage/host which must be isolated from the production environment. Please read the following document for details:
Backing up StarWind Virtual SAN Environment: Best Practice.

Configuring Virtual Tape Library


1. Open StarWind Management Console and select “Add VTL Device”. Select “Create a New Virtual Tape Library” and specify its Name and path to storage.




2. Select the IBM TS03584LTO7 from the drop-down list of the Device Model. Optionally, uncheck “Fill Storage Slots with Empty Tapes after Create” checkbox if you don’t want to fill all empty 60 slots with tapes.




3. Click “Next”.




4. Click “Create”.




5. Once the library creation process is complete, close the wizard.




6. Select the created VTL device, expand it and click “Create Tape”. Specify the Custom path to Tape Files if required and click “Next”.



7. Specify custom barcode if required, select the number of tapes to be created and Tape Type and click “Create”.



The newly created tape will appear in the Tapes section.




In case the tapes should be replicated to the cloud, the StarWind cloud replicator can be used: https://www.starwindsoftware.com/help/Cloudreplicator.html

StarWind Cloud replicator supports Amazon S3 and Amazon Glacier, Backblaze, Microsoft Azure, Wasabi and S3-compatible local object storage which allows to enhance the data protection from ransomware attack or in case of DR cases.


Connecting Vtl On Ibm I Host


For IBM i version 7.3 or higher, use the IBM Navigator for i GUI to create an iSCSI target.

1. Select the IBM i server, right click and select “Manage Node”.




2. Navigate to the “Configuration and Service” tab and select “iSCSI”.






3. Click “Actions” and select “Configure iSCSI target”.




4. Specify the IQN of the created StarWind VTL device and VTL server IP address. Leave the default 3260 port and click “OK”.



5. The pop-up will appear asking to Confirm IOP restart. Select “Yes”.



6. The VTL device should appear as Active and it is ready for use.




NOTE: Please keep in mind that StarWind VTL does not support multipathing and should be connected only via one path.


For older IBM i versions, use the SQL service commands as described below.

Use the IBMi Green Screen option or “Run SQL Scripts” option that can be accessed from the IBM I Access Client under the “Actions” tab.


7. Run select * from table(qsys2.iscsi_info()); to get the StarWind VTL device IQN, Target Host Name and initiator name.



8. Use the following command to set the target of the VTL: call qsys2.add_iscsi_target(target_name=>’target IQN’, target_host_name=>’hostname or ip’);



9. After the iSCSI configuration is done, perform the re-IPL of the virtual IOP associated with the iSCSI connection. An example of the SQL to re-IPL the IOP is below: CALL QSYS2.CHANGE_IOP(IOP=>'ISCSI', OPTION=>'IPL').



Conclusion

Following this guide, a StarWind VTL was deployed and connected to IBM i host, so it could be used for further backup operations and tasks.

Contacts

US Headquarters	EMEA and APAC
+1 617 829 44 95	+44 2037 691 857 (United Kingdom)
+1 617 507 58 45	+49 800 100 68 26 (Germany)
+1 866 790 26 46	+34 629 03 07 17 (Spain and Portugal)
	+33 788 60 30 06 (France)

Customer Support Portal: https://www.starwind.com/support
Support Forum: https://www.starwind.com/forums
Sales: sales@starwind.com
General Information: info@starwind.com

StarWind

StarWind Software, Inc. 100 Cummings Center Suite 224-C Beverly MA 01915, USA
www.starwind.com ©2026, StarWind Software Inc. All rights reserved.